Model Export

HPL3 mainly uses Collada for importing models into the engine binary format, so this guide will only be about the Collada format (.dae). First of there will be some general information that concerns all 3d modelers. After that there will be some more specifics for the mayor packats

General

Setup

<u>Units</u>

Before doing any modelling, make sure that the units are properly set up. It is recommended that 1 unit equal 1 meter or similar. It is also okay that 1 unit = 1 centimeter, but then a 1 meter high object needs to be 100 units high and so on. The engine will automatically adjust any data according to how the units are set up.

Modelling

Setting Material

Always set the diffuse texture of the editor-material to have the same name as the engine-material (.mat) you want it to have. This is best accomplished by always letting the diffuse texture for the material have the same name as the engine-material (e.g. "dirt_road.dds" and "dirt_road.mat"). What happens when the model is loaded is that the engine checks the diffuse texture for the current submesh and then replaces the extention (eg ".dds", ".tga", etc) with ".mat" and then tries to load a material with that file name.

Note: When using the modelviewer, it will automatically create the ".mat"-file if one does not exist, and thus an engine-material does not need to be created by hand if the names of the texture are set up as described here.

Multiple Materials

In order to have a mesh with multiple material you must have several submeshes (or whatever the name of discrete objects in the editor) each with its own material and with different names of the diffuse texture. For example say you are making a character that requires a two materials, one for the hair and one for the body. You then first need to make sure that the hair and body are separate submeshes, then give each one their own material. The body's material can then have the diffuse map: "character_body.dds" and the hair's material can have "character_hair.dss". The engine will now use two different materials to load this character.

Note that this is the only way to go about! It is not possible to have polygon-IDs or whatever tricks the editor might have. One submesh can only have one material!

Animation

Maya

Setup

Collada exporter settings

Here is how the export tool should be set up:

noral options		
File type:	OpenCOLLADA exporter 💌	
	Default file extensions	
eference Options		
	Preserve references	
	Keep only a reference	
	IV Use namespaces	
Prefix with:	the file name 💌	
clude Options		
	Include these inputs:	
	History	
	Channels	
	Expressions Constraints	
	I Constraints	
le Type Specific Optic		
General export opti	Bake transforms	
	Relative paths	Copy textures
	International Provide Prov	1 Copy resides
	Catx file references	
	1. Cyn no rotoroop	
	Sampling	
	Curve constrain	Static curve removal
Filter export		
	Export 🔽 Polygon meshes	✓ Lights
	Cameras	Joints and skin
	Animations	
	Invisible nodes	Default cameras
	Texture coordinates	
	V Normals	Vormals per vertex
	Vertex colors	Vertex colors per vertes
	Texture tangents	Geometric tangents
	Referenced materials only	Materials only
 XRef options 		
	Export references	Pereference
Camera options		
	Export camera as lookat	
	T XFov	VFov
	herXFov and YFov are selected, YFov	e exponea
 Precision options 	Export double precision	
li double a	Export double precision recision is selected, the maximum numb	or of significant
	be printed is increased from 7 to 17 sig	
Export Selection	Apply	Close

(Click for large version)

Modelling

Material fails to export

If the model gets exported without any material check if any of this helps:

1) Check so that "intitialshadingGroup" has not been connected to the model. If it has been, then simple set the same material to the model again and the problem will go away.

2) Check so that two materials have not been set on the same mesh. For having a mesh with multiply material see General/Modelling/Multiple Materials

Animation

3DS Max

Modelling

Animation

Modo

Modelling

Mesh Setup

Every submesh in the scene need to have its own mesh layer and material for the texture and properties to be exported correctly.

<u>Triangulate</u>

The export tool does not triangulate the mesh autoatically so before exporting, you must enter geometry/polygon/triple in order for everything to be triangulated.

Animation

From: https://wiki.frictionalgames.com/ - Frictional Game Wiki

Permanent link: https://wiki.frictionalgames.com/hpl3/engine/model_export?rev=1349166558



Last update: 2012/10/02 09:29